


LIVENCODER INSTALLATION GUIDE


1. System Requirements:

- Windows 7/Server 2008 or above;
- 1Gb RAM;
- 500MB Disk;
- Administrator is required;


2. The first step, run the installation program, agree to the license agreement and the next step:




3. Select the installation directory, you can also follow the default installation directory:




4. Click the install button:



5. After the installation is complete, set up users, click OK and open the Windows user management console, and add the users you need to log in to the LIVENCODER system into the LIVENCODER user group.




6. After installation, the browser will be opened automatically. For the best experience, please install Chrome/FireFox/Edge browser, IE browser is not supported.




7. If you need to access LIVENCODER remotely, please allow TCP port 9090 in the firewall's inbound rules.

8. Enter the user name you chose in step 5, and enter the password to log in:



The screenshot shows the login interface for the LE LIVE ENCODER. It features a blue header with the logo and title. Below the header, there are three input fields: the first contains the username 'bob', the second contains a masked password '.....', and the third is a blue 'Login' button. At the bottom of the page, there is a copyright notice: 'Copyright © 2021 VideoTree Co., Ltd. All rights reserved.'

9. After logging in for the first time, you need to get a license key. Please contact the seller to apply for the license key. When applying for the license key, you need to provide: your company, email address and the Hardware Print (as shown in the figure below):




The screenshot shows the license management page in the LE LIVE ENCODER interface. It has a blue navigation bar with the following menu items: Home, Signal Source, Encode Profile, Stream, Publish, and Quit. The main content area displays the following information:

Version	1.0
License State	5 (Not Activated)
Hardware Print	S1DWzGR3+xE=
License Key	<input type="text"/>

Below the License Key field is a blue 'Update License' button. At the bottom of the page, there is a copyright notice: 'Copyright © 2021 VideoTree Co., Ltd. All rights reserved.'

10. After obtaining the license key, fill in the License Key field and click the Update License button:




The screenshot shows the 'License' page of the VideoTree software. The top navigation bar includes 'Home', 'Signal Source', 'Encode Profile', 'Stream', 'Publish', and 'Quit'. The main content area displays the following information:

Version	1.0
License State	5 (Not Activated)
Hardware Print	S1DWzGR3+xE=
License Key	wRSUO/8HbpqXlsAGid9y9/N/bEusyFItIESeWfNd/d82q9KcUIYvj8LkP0mPey/QdG7KfjqKRsOIKiS8O8YUsltjoC7N/TPfHYRna8bb5wuhF6AG8CnIr44N7B+R0Fif/e7wayghjgQ=="

Below the license key is an 'Update License' button. At the bottom of the page, the copyright notice reads: 'Copyright © 2021 VideoTree Co., Ltd. All rights reserved.'

11. When the activation is successful, you will get the following interface, please make sure that the License State is 0 (Normal):



The screenshot shows the 'License' page after successful activation. The top navigation bar is the same. The main content area displays the following information:

Version	1.0
License State	0 (Normal)
Hardware Print	S1DWzGR3+xE=
License Hardware Print	S1DWzGR3+xE=
Product Code	LIVENCODER
License Type	trial
Serial No.	LIVENCODER_00001
Expires At	Fri Aug 13 2021 00:00:00 GMT+0
License Key	

Below the license key field is an 'Update License' button. At the bottom of the page, the copyright notice reads: 'Copyright © 2021 VideoTree Co., Ltd. All rights reserved.'